

PIM SSM with default group 232.0.0.0/8

All routers

Interface config

```
int xxx
ip ospf 1 area 0
ip pim sparse-mode
exit
```

```
ip multicast-routing
ip pim ssm default
```

LHR

The interface that is connected to receiver

```
int xxx
ip igmp ver 3
exit
```

SSM with non default

All routers

```
access-list 1 permit host 239.1.1.1
ip pim ssm range 1
```

REC

```
int e0/0
ip igmp ver 3
ip igmp join-group 232.1.1.1 source 10.1.1.1
ip igmp join-group 232.1.1.1 source 1.1.1.1
```

Non Default

```
int e0/0
ip igmp join-group 239.1.1.1 source 10.1.1.1
```

PIM BIDIR

All routers/All interfaces

ip multicast-routing

```
int xxx
ip ospf 1 area 0
ip pim sparse-mode
exit
```

R3: Rp

```
ip pim bidir-enable
ip pim send-rp-announce lo0 scope 10 bidir
ip pim send-rp-discovery lo0 scope 10
ip pim autorp listener
```

All others

```
R3: Rp  
ip pim bidir-enable  
ip pim autorp listener
```

```
=====  
MSDP
```

```
R1: Rp for Multicast Domain 1
```

```
ip pim bsr-candidate Loopback0 0  
ip pim rp-candidate Loopback0
```

```
! MSDP config  
ip msdp peer 3.3.3.3 connect-source Loopback0
```

```
int s2/0  
ip pim bsr-router  
exit
```

```
All routers  
ip multicast-routing
```

```
int xxx  
ip ospf 1 a 0  
ip pim sparse-mode  
exit
```

```
R3: Rp for Multicast Domain 2
```

```
ip pim bsr-candidate Loopback0 0  
ip pim rp-candidate Loopback0
```

```
! MSDP config  
ip msdp peer 1.1.1.1 connect-source Loopback0
```

```
int s2/0  
ip pim bsr-router  
exit
```

```
All routers  
ip multicast-routing
```

```
int xxx  
ip ospf 1 a 0  
ip pim sparse-mode  
exit
```

```
=====  
MSDP with anycast
```

```
R1/R3 (MSDP peers)
```

```
int s2/0  
no ip pim bsr-border
```

exit

```
ip pim bsr-candidate Loopback0 0
ip pim rp-candidate Loopback 1
```

int lo 1

```
ip add 88.88.88.88 255.255.255.255
```

```
ip ospf 1 area 0
```

```
ip pim sparse-mode
```

exit

MSDP

R1

```
ip msdp peer 3.3.3.3 connect-source Loopback0
```

R3

```
ip msdp peer 1.1.1.1 connect-source Loopback0
```